


iperclass.net

- Application étudiante pour l'enseignement à distance -

User instructions

Version 7.5.3 - Updated on September 15, 2020



← Launch the application from this link on the desktop.

A screenshot of the IperClass application window. The window title is 'IperClass'. It contains several input fields and buttons. The 'Classroom ID' field is filled with 'ITC VittEmanII Bergamo3'. The 'Password' field is empty. The 'Student name' field is filled with 'Rossi Mario'. The 'Room' field is filled with '3'. The 'Status' field is filled with 'Disconnected'. There are buttons for 'Connect', 'Disconnect', 'Delete', and 'Auto'. Below these fields is a list of 'Saved classrooms' with the following entries: 'ITC VittEmanII Bergamo1', 'ITC VittEmanII Bergamo2', 'ITC VittEmanII Bergamo3', 'ITC VittEmanII Bergamo4', 'ITC VittEmanII Bergamo5', 'Cristina.Andreoli.Italiano', 'andrea.prosperi.fisica', and 'luigigualandi-chimica'.

“**Classroom ID**”:

- 1) To connect to a classroom of the school, you should have the name of the institute, the town and the number of the “Room”, a number between 1 and 98. In absence of this final number, it is assumed that the teacher is teaching from his home and the number 1 will be set by default.
- 2) To connect to a teacher at his home, he will give you his identification name without a final number. The Room will then be the n. 1 by default.

“**Password**”:

“**Student name**”:

Clicking on «**Connect**», you will pass from «**Unconnected**» to «**Connecting ...**» and, in few seconds, to «**Connected**». The image of the teacher will appear in a little window. An initial 8-second disconnection is possible to search for the best mode.

To connect a class ID already stored in "Saved classrooms" list, double-click on it.



When you connect to the teacher, his webcam will appear in your screen and your desktop will appear in the teacher management panel, showing the name.

The teacher will see the desktops of the whole class at the same time to check the progress of the activities.

The teacher can switch to see the webcams of students instead of their desktops, to verify their identity (your webcam light will turn on).



If you are not recognized, the teacher can refuse your connection.

Leave the upper right corner of your desktop free of icons where teacher's webcam will be shown.



A right click on the icon located in the Systray allows you to access the help request.



This link on the desktop opens the "StudentWorks" folder created on the C: drive to be common to all accounts. It is a folder used for the temporary transit of the files of the exercises that the teacher sends you or that must collect. The exercise must be saved leaving the same file name, because the transfer system will personalize the file name by adding the student's name. In any case, it is recommended to include your name also in the text of the exercise.

Installation

- 1) Download the installer from the website www.iperclass.net
- 2) **Disable the antivirus** (except Windows Defender, which does not create problems).
- 3) Launch the installer. Do **not** install **Framework.net** as proposed by Windows. It's not necessary.



Please note that with the same internet connection it is possible to launch Iperclass from only one computer at a time. Two students cannot launch two Iperclass using the same Internet connection.



Audio

To prevent the sounds emitted by the loudspeaker from entering the microphone, creating a loop and his consequent whistle, for listening it is recommended to use a simple headset, even without microphone, which can remain the one built into the PC.

The important thing is that no speakers are used, neither the internal speakers of the PC, nor any external speakers, to avoid that their powerful sound enters the microphone.

You can check that the sound is not entering the microphone using the Windows "Listen to this device" function.






Listen to your microphone with the two levels set to maximum:

- if you listen to it from the speakers, a whistle will sound.
- if you listen from a headset (or the smartphone earpiece, for which the unified socket is required, or Bluetooth), there will be no whistle and the solution adopted will be the correct one.

Troubleshooting

The best proof of the successful connection is the presence of the teacher's living image. If it is frizzy or absent, close the app, check your Internet browsing and try again.

If necessary, replace the "Auto" mode with the "Relay" one.



In case the app doesn't open > right click on the taskbar > Task manager> More details > check that there are processes with the name Capturix still

running > close them by the key "Del" or right clicking on each of them > End task > restart Iperclass.